

Global configuration - Security

The screenshot shows the Jira Administration interface. At the top, there is a search bar for 'Search Jira admin' and a navigation menu with 'Add-ons' selected. The left sidebar lists various configuration categories like 'ATLASSIAN MARKETPLACE', 'BIGTEMPLATE', and 'BIGPICTURE'. The main content area is titled 'Security' and contains two radio button options: 'Permissions for everyone' (unselected) and 'Default Roles' (selected). Below the options are 'Save' and 'Assign Roles' buttons.

Security - Permissions for everyone

By the default 'Permissions For Everyone' is enabled. While it is ON every logged in user has the same (Administrative) level of permissions to all programs while working with the application and the per program Roles will be disabled:

The screenshot shows the 'Security' configuration page with a breadcrumb trail: 'Program Manager > Global Teams > Administration > Security > Documentation'. The 'Global Roles' section is active. A blue information box contains the following text: 'Permissions for everyone in plugin global configuration is enabled. If you want to change this settings either way, contact your Administrator.'

This setting is useful when managing small projects or while evaluating our plugin. It is easier to test and learn how things work but a live environment may require more advanced access control.

Security - Default Roles

[Global Roles](#)
Security ?

By default, everyone has access to everything. However, you can fine-tune things quite considerably. Let assign users and groups to 5 different levels of permissions.

NAME	CODE	DESCRIPTION	ACTIONS
> Admin 2	ADMN	Main administrator, has all access	
v Global Program Admin 2 > Users 2 > Groups 0	GLAD	Has access to program configuration	
> Global Program Creator 2	GLCR	Can create programs	
> Global Editor 0	GLER	Can edit tasks program	
> Global User 4	GLUS	Read only access to program	

After clicking the "Assign roles" button, you will be redirected to global security screen where you can grant access to all plugin programs (except for private programs as described below). It is possible to assign the following Roles to individual Users or Groups:

Role	Description
Admin	Understood as Global admin or Main administrator, has access to all sections.
Program admin	Has access to program configuration. Can configure, edit programs, edit program tasks and view programs.
Program creator	Can create programs, edit programs, edit tasks and view programs.
Program editor	Can edit program tasks.
Program user	Read only access to programs. Cannot edit anything. In this mode the user will see the "read only" icon next to the program name.